

SAMPLE	KF	EY/SKU	QTY	CUT
	A	Call Me Red <i>3714-10</i>	1 1/8 yd	(4) 7 ½" x wof strips, subcut (17) 7 ½" hexagons
50	В	Call Me Black 3714-12	7/8 yd	(3) 7 ½" x wof strips, subcut (15) 7 ½" hexagons
	С	Call Me Tan 3714-07	1 1/8 yd	(4) 7 ½" x wof strips, subcut (20) 7 ½" hexagons
	D	Line Art Tan 3717-07	7/8 yd	(3) 7½" x wof strips, subcut (14) 7½" hexagons
	E	On the Dot Red 3716-10	718 yd	(3) 7 ½" x wof strips, subcut (15) 7 ½" hexagons
	F	On the Dot Black 3716-12	7/8 yd	(3) 7 ½" x wof strips, subcut (11) 7 ½" hexagons
	G	Where To? Tan <i>3715-07</i>	5/8 yd	(2) 7 ½" x wof strips, subcut (8) 7 ½" hexagons
	Н	Call Me Turquoise 3714-84	1 1/8 yd	(4) 7 ½" x wof strips, subcut (16) 7 ½" hexagons
	I	Where To? Black 3715-12	1 yd	(7) 1 ¾" x WOF strips (borders) (7) 2 ¼" x WOF strips (binding)

 $WOF = Width \ of \ Fabric$ 

QUILT DIAGRAM. G D В C В G D A C C Ē В D F Н В C A Н н В E E C C A н D C н G В G F Border Н C G C C A E A C В Н E A C н F A C В Н A C G D G Н C C

I Border

# **QUILT CENTER ASSEMBLY:**

STEP 1: On the wrong side of the fabric, using a marking pen, pencil or chalk, — mark the 1/4" point in all corners of the hexagon.

STEP 2: Referring to omer point to comer point to the quilt diagram for color placement and working diagonally, sew the rows of hexagons together. Begin the seam at the corner point and continue to the next corner point.

Taking a back stitch at each place, press seam open.

Draw 1/4" seam allowance

line on each edge.

Mark each corner point.

STEP 3: Once the diagonal rows are sewn, begin sewing the rows together. Use the center point mark to pivot at each corner. Press seams open. Continue sewing 2 rows together, then join sets together until all rows are sewn together. Note that there are some hexagons that will hang past the other blocks, these will be trimmed off in squaring the quilt. Press all seams open.

**STEP 4:** Referring to the blue dashed lines on the quilt diagram, draw a straight line down each side of the quilt. Make sure there is a 1/4" allowance. Trim quilt on the line. Repeat for the top and bottom of quilt.

### **BORDER ASSEMBLY**

Measure width and length of quilt top to ensure border cutting sizes. Below are our measurements.

**STEP 5:** I Border for quilt sides – 1 ¾" x (70 ½") Sew (2) WOF border strips together at short ends. Sew border to (1) side of quilt and trim even with quilt edges. Use remaining portion of strip and sew to next WOF Sew to other side of quilt.

I Border for quilt top and bottom−1 ¾" x (60") *Repeat steps above.* 

#### **FINISHING**

Cut batting and backing 3" larger than top on all sides. Layer backing, batting and top together and baste or pin. When quilting is completed, trim excess batting and backing. Bind as usual.

## FINISHED QUILT SIZE: 60" x 74"

Note: If this Benartex pattern is included in a kit, any questions about the kit should be addressed to the vendor from whom you bought it.

## **TEMPLATE:**

Trace template on to plastic template material. Mark top and bottom and check measurements as shown on diagram.

